

# EMV Gate Heartbeat – Technical Specification (EN)

## EMV Gate Heartbeat – Technical Specification (EN)

**1) Overview** This document specifies a lightweight HTTP-based heartbeat for EMV Gate devices and the desktop monitor app (Electron + React). Devices periodically POST their status to a local HTTP server running inside the app. The app also watches a device list file and merges that with the latest heartbeat.

**\*\*Default port:\*\*** `3070` (configurable via `config.json` → `heartbeatPort`, if present)

**\*\*Device file path:\*\*** `device-communication.json` (absolute or resolved from `deviceCommunicationPath` in `config.json`).

---

**2) JSON Payload** ``jsonc { "id": "G1-01", // Unique device id "ip": "192.168.1.101", // Device IP "status": "online", // "online" | "offline" | "fault" | "maintenance" "ts": "2025-08-14T13:31:52Z" // ISO-8601 UTC (Z) } ``

### Required fields

- **\*\*id\*\***: string (unique ID known by the monitor app)
- **\*\*ip\*\***: IPv4/IPv6 string
- **\*\*status\*\***: enum: `online`, `offline`, `fault`, `maintenance`
- **\*\*ts\*\***: ISO-8601 UTC timestamp, e.g. `2025-08-14T13:31:52Z`

> If `ts` is omitted, the server may fallback to current server time.

---

### 3) HTTP Endpoints

### 3.1 POST `/hb`

Accepts a single heartbeat event.

**\*\*Request headers\*\***

---

Content-Type: application/json

---

**\*\*Request body\*\***

See JSON payload above.

**\*\*Response 200\*\***

``json  
{ "ok": true }  
``

**\*\*Response 400\*\***

``json  
{ "ok": false, "error": "Invalid payload" }  
``

---

### ### 3.2 GET `/devices`

Returns the current device list with last known heartbeats merged.

**\*\*Response 200\*\***

```
```json
{
  "ok": true,
  "devices": [
    {
      "id": "G1-01",
      "name": "Entry Reader 01",
      "side": "north",
      "gateId": "G1",
      "deviceIp": "192.168.1.101",
      "status": "online",
      "lastHeartbeat": "2025-08-14T13:31:52Z"
    }
  ]
}
```
```

> The app also watches the `device-communication.json` file. If that file exists and is an array of device objects, fields are merged and then updated by the latest heartbeat.

---

## 4) Device File (`device-communication.json`) **\*\*Format:\*\*** JSON array of devices.

```
json [ { "id": "G1-01", "name": "Entry Reader 01", "side": "north", "gateId": "G1", "deviceIp": "192.168.1.101", "status": "online", "lastHeartbeat": "2025-08-14T13:31:52Z" } ]
```

If the app sees an *object* with `devices: [...]`, it will fallback to the inner array; otherwise it expects a top-level array. Always prefer the **\*\*array\*\*** format.

---

## 5) Effective Status Logic The UI shows **\*\*effective status\*\*** (derived from heartbeat + TCP probe):

- **\*\*Input\*\***
- Heartbeat status → `online | offline | stale` (stale = no heartbeat for `staleMs`, offline = no heartbeat for `offlineMs`).
- TCP probe (`probeTcp(host, port, timeout)`): `reachable: true|false` on port `22` by default.
- **\*\*Decision** (recommended “A” mapping)
- If device status is `maintenance` → **\*\*maintenance\*\***.
- If heartbeat is `offline` → probe reachable? **\*\*fault\*\*** : **\*\*offline\*\***.
- If heartbeat is `stale` → probe reachable? **\*\*online\*\*** : **\*\*offline\*\***.
- If heartbeat is `online` → probe not reachable? **\*\*fault\*\*** : **\*\*online\*\***.

**\*\*Defaults:\*\*** `staleMs=60000`, `offlineMs=300000`, `tcpPort=22`, `timeoutMs=1200`.

---

## 6) Testing

### ### 6.1 cURL

```
```bash
```

```
# Send one heartbeat (local dev server)
```

```
curl -sS -X POST http://127.0.0.1:3070/hb -H 'Content-Type: application/json' -d
'{"id":"G1-01","ip":"192.168.1.101","status":"online","ts":"2025-08-14T13:31:52Z"}
```

## Query merged devices curl -sS http://127.0.0.1:3070/devices | jq ``

```
### 6.2 TCP checks (manual)
``bash
# TCP reachability
nc -vz -w 2 192.168.1.101 22 ; echo $?
# SSH attempt (expect auth error but proves reachability)
ssh -o ConnectTimeout=2 -o BatchMode=yes -p 22 user@192.168.1.101 exit
``
```

```
### 6.3 Postman
1. Import the provided **Collection** and **Environment** files.
2. Set `{{baseUrl}}` to `http://127.0.0.1:3070` or your server IP.
3. Run `HB: POST /hb` then `GET /devices` to verify merge.
```

---

**7) Error Handling - Invalid JSON** → `400 { "ok": false, "error": "Invalid payload" }` - **Missing fields** → `400 { "ok": false, "error": "Missing id/ip/status/ts" }` - **Internal errors** → `500 { "ok": false, "error": "" }`

---

**8) Security Notes** - The heartbeat server is intended for **\*\*trusted LAN\*\*** only. - If needed, implement IP allowlist or a shared secret in a header. - Consider rotating logs and not storing credentials in plain text.

---

**9) Appendix — Sample `config.json`** ``json { "environment": "development", "logsPath": "./logs", "logsRetentionDays": 14, "logLevel": "info", "deviceCommunicationPath": "./data/device-communication.json", "heartbeatPort": 3070, "fullScreen": false } ``